


Hardware Control course--Ultrasonic ranging

1. Learning target


In this course, we will learn how to use ultrasonic ranging.

2. Principle of experimental

The ultrasonic module is a sensor that uses ultrasonic characteristics to detect the distance. It has two ultrasonic probes for transmitting and receiving ultrasonic waves. The range of measurement is 3-450 cm.



(1) You need to input a high level signal of at least 10us to the Trig pin to trigger the ranging function of the ultrasonic module.



(2) After the ranging function is triggered, the module will automatically send out 8 ultrasonic pulses with 40 kHz and automatically detect whether there is a signal return. This step is done internally by the module.



(3) When the module detects an echo signal, the ECHO pin will output a high level. The high level duration is the time from when the ultrasonic wave is sent to when it returns. You can calculate the distance by using the time function to calculate the high level duration.

Formula: Distance = High level duration * Speed of sound(340M/S)/2.


3. Coding method

In this course, we use BOARD coding method.

According to the hardware interface manual, we see that the ultrasonic Echo and Trig pins are connected to the 18 and 16 pin of the Raspberry Pi board.

The pin comparison table of Raspberry Pi as shown below.





wiringPi	всм	Function	BOARD		Function	ВСМ	wiringPi
		3.3V	1	2	5V		
8	2	SDA.1	3	4	5V		1
9	3	SCL.1	5	6	GND	1	
7	4	GPIO.7	7	8	TXD	14	15
		GND	9	10	RXD	15	16
0	17	GPIO.0	11	12	GPIO.1	18	1
2	27	GPIO.2	13	14	GND		
3	22	GPIO.3	15	16	GPIO.4	23	4
		3.3V	17	18	GPIO.5	24	5
12	10	MOSI	19	20	GND		
13	9	MISO	21	22	GPIO.6	25	6
14	11	SCLK	23	24	CE0	8	10
		GND	25	26	CE1	7	11
30	0	SDA.0	27	28	SCL.0	1	31
21	5	GPIO.21	29	30	GND		
22	6	GPIO.22	31	32	GPIO.26	12	26
23	13	GPIO.23	33	34	GND		
24	19	GPIO.24	35	36	GPIO.27	16	27
25	26	GPIO.25	37	38	GPIO.28	20	28
		GND	39	40	GPIO.29	21	29

4. About code

Path: /home/pi/Yahboom project/Raspbot/2.Hardware Control course/4.Ultrasonic



ranging

1) Import time and GPIO library

```
import RPi.GPIO as GPIO
import time
```

2) Ignore warning

```
GPIO.setwarnings(False)
```

3)Define the pins of the ultrasonic module

```
EchoPin = 18
TrigPin = 16
```

4)Set the coding method of the pin, and set the modes of the Echo and Trig pins

```
GPIO.setmode(GPIO.BOARD)

GPIO.setup(EchoPin,GPIO.IN)
GPIO.setup(TrigPin,GPIO.OUT)
```

5) Define the ultrasonic ranging function

We need to set a high level signal of at least 10us to the TRIG pin of the ultrasonic module to trigger the module's ranging function.

```
def Distance():
   GPIO.output(TrigPin,GPIO.LOW)
   time.sleep(0.000002)
   GPIO.output(TrigPin, GPIO.HIGH)
   time.sleep(0.000015)
   GPIO.output(TrigPin,GPIO.LOW)
   t3 = time.time()
   while not GPIO.input(EchoPin):
       t4 = time.time()
       if (t4 - t3) > 0.03:
           return -1
   t1 = time.time()
   while GPIO.input(EchoPin):
       t5 = time.time()
       if(t5 - t1) > 0.03:
           return -1
   t2 = time.time()
   time.sleep(0.01)
   #print ("distance_1 is %d" % (((t2 - t1)* 340 / 2) * 100))
   return ((t2 - t1)* 340 / 2) * 100
```

5. Running code

Click the button shown in the figure below to run the program on the Jupyter Lab



interface



6. Experimental phenomenon

After the program runs, we can see that distance will be printed on JupyterLab.