

Path:

/home/pi/Yahboom_project/Raspbot/3.AI Vision course/01.Drive camera/Drive camera.ipynb

Common API functions used by OpenCV:

1. cv2.VideoCapture()

cap = cv2.VideoCapture(0)

The parameter in VideoCapture () is 0, which means Raspberry Pi video0.

(Note: You can view the current camera through the command `ls/dev/`)

```
pi@raspberrypi:~ $ ls /dev/
argon-h264mem  media1      shm         tty38       vcio
argon-hevcmmem mem          snd         tty39       vc-mem
argon-intcmem  memory_bandwidth spidev0.0   tty4        vcs
argon-vp9mem   mmcblk0     spidev0.1   tty40       vcs1
autofs         mmcblk0p1   stderr      tty41       vcs2
block          mmcblk0p2   stdin       tty42       vcs3
btrfs-control  mqueue     stdout      tty43       vcs4
bus            net         tty         tty44       vcs5
cachefiles     network_latency tty0         tty45       vcs6
char           network_throughput tty1         tty46       vcs7
console        null        tty10        tty47       vcsa
cpu_dma_latency port        tty11        tty48       vcsa1
cuse           ppp         tty12        tty49       vcsa2
disk           ptmx        tty13        tty5        vcsa3
dri            pts         tty14        tty50       vcsa4
fb0            ram0        tty15        tty51       vcsa5
fd             ram1        tty16        tty52       vcsa6
full           ram10       tty17        tty53       vcsa7
fuse           ram11       tty18        tty54       vcsm
gpiochip0      ram12       tty19        tty55       vcsm-cma
gpiochip1      ram13       tty2         tty56       vcsu
gpiochip2      ram14       tty20        tty57       vcsu1
gpiomem        ram15       tty21        tty58       vcsu2
hwrng          ram2        tty22        tty59       vcsu3
i2c-1          ram3        tty23        tty6        vcsu4
initctl        ram4        tty24        tty60       vcsu5
input          ram5        tty25        tty61       vcsu6
kmsg           ram6        tty26        tty62       vcsu7
log            ram7        tty27        tty63       vga_arbiter
loop0          ram8        tty28        tty7        vhci
loop1          ram9        tty29        tty8        video0
loop2          random      tty3         tty9        video1
loop3          raw         tty30        ttyAMA0     video10
loop4          rfkill      tty31        ttyprintk   video11
loop5          rpivid-h264mem tty32        ttyS0       video12
loop6          rpivid-hevcmmem tty33        uhid        watchdog
loop7          rpivid-intcmem tty34        uinput      watchdog0
loop-control   rpivid-vp9mem tty35        urandom     zero
mapper         serial0     tty36        v4l         vchiq
media0         serial1     tty37        vchiq
```

cap = cv2.VideoCapture("../1.avi")

VideoCapture("../1.avi"), This parameter indicates that if the path of the video file is entered, the video is opened.

2. cap.set()

Camera parameters common configuration methods:

capture.set(CV_CAP_PROP_FRAME_WIDTH, 1920); # Width

```
capture.set(CV_CAP_PROP_FRAME_HEIGHT, 1080); # Height
capture.set(CV_CAP_PROP_FPS, 30); # Frame
capture.set(CV_CAP_PROP_BRIGHTNESS, 1); # Brightness 1
capture.set(CV_CAP_PROP_CONTRAST, 40); # Contrast 40
capture.set(CV_CAP_PROP_SATURATION, 50); # Saturation 50
capture.set(CV_CAP_PROP_HUE, 50); # Hue 50
capture.set(CV_CAP_PROP_EXPOSURE, 50); # Visibility 50
```

Parameter explanation:

```
#define CV_CAP_PROP_POS_MSEC 0
// Calculate the current position in milliseconds
#define CV_CAP_PROP_POS_FRAMES 1
// Calculate the current position in frame
#define CV_CAP_PROP_POS_AVI_RATIO 2 // Relative position of the video
#define CV_CAP_PROP_FRAME_WIDTH 3 // Width
#define CV_CAP_PROP_FRAME_HEIGHT 4 // Height
#define CV_CAP_PROP_FPS 5 // Frame rate
#define CV_CAP_PROP_FOURCC 6 // 4 Character encoding
#define CV_CAP_PROP_FRAME_COUNT 7 // Video frames
#define CV_CAP_PROP_FORMAT 8 // Video format
#define CV_CAP_PROP_MODE 9
// Backend specific value indicating the current capture mode.
#define CV_CAP_PROP_BRIGHTNESS 10 // Brightness
#define CV_CAP_PROP_CONTRAST 11 // Contrast
#define CV_CAP_PROP_SATURATION 12 // Saturation
#define CV_CAP_PROP_HUE 13 // Hue
#define CV_CAP_PROP_GAIN 14 // Gain
#define CV_CAP_PROP_EXPOSURE 15 // Exposure
#define CV_CAP_PROP_CONVERT_RGB 16
// Mark whether the image should be converted to RGB.
#define CV_CAP_PROP_WHITE_BALANCE 17 // White balance
#define CV_CAP_PROP_RECTIFICATION 18 // Stereo camera calibration mark (note:
only support DC1394 v2)
```

3. `cap.isOpened()`

Return true indicates open camera successful and false indicates open camera failure

4. `ret, frame = cap.read()`

`cap.read ()` reads the video frame by frame. `ret` and `frame` are the two return values of the `cap.read ()` function.

`ret` is a Boolean value, if the read frame is correct, it will return true, If the file has not been read to the end, it returns False.

`Frame` is the image of each frame, which is a three-dimensional matrix.

5. cv2.waitKey(n)

n represents the delay time, if the parameter is 1, it means a delay of 1ms to switch to the next frame of image.

If the parameter is too large, such as cv2.waitKey (1000), it will freeze because of the long delay.

The parameter is 0, such as, cv2.waitKey (0) only displays the current frame image, which is equivalent to video pause.

6. cap.release() and destroyAllWindows()

Call cap.release () to release the video.

Call destroyAllWindows () to close all image windows.

About Code

Since our entire tutorial runs in JupyterLab, we must understand the various components inside.

Here we need to use the image display component.

1.Import library

```
import ipywidgets.widgets as widgets
```

2.Set Image component

```
image_widget = widgets.Image(format='jpeg', width=600, height=500)
```

3.Display Image component

```
display(image_widget)
```

4.Open camera and read image

```
image = cv2.VideoCapture(0)      # Open camera
ret, frame = image.read()        # Read camera data
```

5.Assignment to components

#Convert the image to jpeg and assign it to the video display component

```
image_widget.value = bgr8_to_jpeg(frame)
```

```
import cv2
import ipywidgets.widgets as widgets
import threading
import time

#Set camera display component
image_widget = widgets.Image(format='jpeg', width=600, height=500)
display(image_widget)      # display camera component

#bgr 8 to jpeg format
import enum
```

```

import cv2

def bgr8_to_jpeg(value, quality=75):
    return bytes(cv2.imencode('.jpg', value)[1])

image = cv2.VideoCapture(0)          # Open camera

# width=1280
# height=960
# cap.set(cv2.CAP_PROP_FRAME_WIDTH,width)  # set width of image
# cap.set(cv2.CAP_PROP_FRAME_HEIGHT,height) # set height of image

image.set(3,600)
image.set(4,500)
image.set(5, 30)  # set frame
image.set(cv2.CAP_PROP_FOURCC, cv2.VideoWriter_fourcc('M', 'J', 'P', 'G'))
image.set(cv2.CAP_PROP_BRIGHTNESS, 40)  #set brightness -64 - 64  0.0
image.set(cv2.CAP_PROP_CONTRAST, 50)    #set contrast -64 - 64  2.0
image.set(cv2.CAP_PROP_EXPOSURE, 156)  #set exposure value 1.0 - 5000 156.0

ret, frame = image.read()              # read camera data
image_widget.value = bgr8_to_jpeg(frame)

while 1:
    ret, frame = image.read()
    image_widget.value = bgr8_to_jpeg(frame)
    time.sleep(0.010)

image.release()  #After using the object, we need to release the object, otherwise
when we use the object again, the system will prompt that the object be occupied,
making it unusable.

```

The camera screen is shown below:

